

Network Shared Folder (SMB v2.0)

The account cannot be anonyms.


1. Network sharing settings
   - Step 1 : Right-click the Wi-Fi icon and select "Network & Internet" settings
   - Step 2 : Select "Network and Sharing Center" (Win 10), select "Dial" and then click "Network and Sharing Center" (Win 11).




   - Step 3 : Click "Advanced sharing settings" on the left
   - Step 4 : Turn on "Public Data Sharing" under All Networks




2. Folder sharing
   - Step 1 : Right-click the folder and select "Contents" to switch to the "Sharing" page




- Click on "Advanced Sharing"
- Click on "Permissions"





- Click on "Add ..."




- Click on "Advanced ...” , and then click "Find Now".




Select Users or Groups
Select this object type:
Users, Groups, or Built-in security principals
Object Types...
From this location:
LAPTOP-6CJFF7J2
Locations...
Common Queries
Name:
Starts with
Description:
Starts with
Disabled accounts
Non expiring password
Days since last logon:
Columns...
Find Now
Stop
OK
Cancel
Search results:
Name
In Folder


Select Users or Groups
Select this object type:
Users, Groups, or Built-in security principals
Object Types...
From this location:
LAPTOP-6CJFF7J2
Locations...
Common Queries
Name:
Starts with
Description:
Starts with
Disabled accounts
Non expiring password
Days since last logon:
Columns...
Find Now
Stop
OK
Cancel
Search results:
Name
In Folder
__vmware__
LAPTOP-6CJFF...
Aco
LAPTOP-6CJFF...
Administrator
LAPTOP-6CJFF...
Administrators
LAPTOP-6CJFF...
ALL APPLICATION PACKAG...
ANONYMOUS LOGON
Authenticated Users
BATCH
CONSOLE LOGON
CREATOR GROUP

- Search for your username and select it. You can also select Authenticated Users in the list, which can be accessed by authenticated users of the computer. Click "OK" and check "Full Control" in the permission box, and click "Confirm" to complete the setting.



※ Console\All Console Projects\User Accounts\Management Accounts. Make sure that the user name and password entered in the remote configuration in the Apache App match the computer


※ Password setup path: Set > Account > login options
If this option is not available, try Microsoft the login password

Configure remote folder in Apache App

Follow these steps to set up a remote shared folder.

1. Click the Menu icon in the upper left corner.

2. Select Settings




3. Click the edit icon next to "Export to remote location". 

4. Fill in the information in the appropriate setting fields



5. Press Test to verify communication with the remote folder.



Press "Save" to save the settings.

If communication is successfully established, a message "Successfully connected to server" will be displayed.

If communication fails, verify that the information entered is correct and that the computer and mobile device are connected to the same **area network**.